

Conversion/Interface	Interface Tables	Base Tables	Open Interface/Concurrent Program	APIs	
Items	MTL_SYSTEM_ITEMS_INTERFACE	MTL_SYSTEM_ITEMS_B MTL_SYSTEM_ITEMS_TL	Item Open Interface		
Item Categories	MTL_ITEM_CATEGORIES_INTERFACE	MTL_ITEM_CATEGORIES	Item Open Interface		
Item Cost	CST_ITEM_CST_DTLS_INTERFACE	CST_ITEM_COST_DETAILS	The Import Cost Option		
	CST_ITEM_COSTS_INTERFACE	CST_ITEM_COSTS			
Category Codes		MTL_CATEGORIES_B MTL_CATEGORIES_TL		inv_item_category_pub.create_category	
Customer Items	MTL_CI_INTERFACE	MTL_CUSTOMER_ITEMS	Customer Item Interface		
On Hand Quantities	MTL_TRANSACTIONS_INTERFACE				
	MTL_TRANSACTIONS_LOTS_INTERFACE	MTL_MATERIAL_TRANSACTIONS	Item Transaction Open Interface		
Item Pricing		QP_LIST_HEADERS QP_LIST_LINES QP_PRICING_ATTRIBUTES		qp_price_list_pub.process_price_list	
		OE_ORDER_HEADERS_ALL OE_ORDER_LINES_ALL		oe_order_pub.process_order	
		OE_SALES_CREDITS			
Sales Order					
Sales Order Notes		FND_DOCUMENTS FND_DOCUMENTS_TL FND_DOCUMENTS_LONG_TEXT FND_DOCUMENTS_SHORT_TEXT		fnd_documents_pkg.insert_row ow	
	AR-Open Invoices	RA_INTERFACE_LINES_ALL	RA_CUSTOMER_TRX_LINES_ALL	Autoinvoice Import Program	
	PO (Open: Standard & Blanket)	PO_HEADERS_INTERFACE	PO_HEADERS_ALL	Import Standard Purchase Orders	
		PO_LINES_INTERFACE	PO_LINES_ALL	Import Price Catalogs	
PO_DISTRIBUTIONS_INTERFACE		PO_DISTRIBUTIONS_ALL			
Customer		HZ_PARTIES HZ_PARTY_SITES HZ_PARTY_SITE_USES HZ_CUST_ACCT_SITES_ALL		hz_party_v2pub.create_organization hz_location_v2pub.create_location hz_party_site_v2pub.create_party_site_use hz_contact_point_v2pub.create_contact_point ccount hz_cust_account_site_v2pub.create_cust_acct_site	
	HR Organizations		ORG_ORGANIZATION_DEFINITIONS	ation on	
	Employees (Person/Assignment/Address)			hr_employee_api.create_employee hr_person_api.update_us_person hr_ex_employee_api.actual_termination_emp p hr_assignment_api.update_emp_asg	

				hr_assignment_api.update_emp_asg_criteria
				hr_location_api.create_location
				hr_address_api.create_person_addresses
				hr_person_address_api.update_person_addresses
				hr_person_address_api.create_person_addresses
GL Code Combinations	GL_INTERFACE	GL_CODE_COMBINATIONS	JOURNAL IMPORT	Use GL_INTERFACE to load the Code Combination Id and for this purpose we shall be entering the Journal entries with amount as 0 and we shall be able to enter the Journal entries and inturn load the Code Combinations only if for this structure "Allow Dynamic Inserts" is enabled. We don't have to bother about duplicate entries. They will be automatically take care off.
GL FLEX VALUES		FND_ID_FLEX_STRUCTURES		ue
		FND_ID_FLEX_SEGMENTS		fnd_flex_loader_apis.up_val_norm_hierarchy
		FND_FLEX_VALUE_SETS		
		FND_FLEX_VALUES		
		FND_FLEX_VALUE_NORM_HIERARCHY		
AP INVOICES	AP_INVOICES_INTERFACE	AP_INVOICES_ALL	Payables Import Program	
QA RESULTS	AP_INVOICE_LINES_INTERFACE	AP_INVOICE_DISTRIBUTIONS_ALL		Collection Import
TRADING PARTNERS		ECE_TP_HEADERS		
		ECE_TP_LINES		
Project Expenditures	PA_TRANSACTION_INTERFACE_ALL	PA_EXPENDITURES_ALL	Transaction Import	
		PA_EXPENDITURE_GROUPS_ALL		
		PA_EXPENDITURE_ITEMS_ALL		
		PA_COST_DISTRIBUTION_LINES_ALL		
		PA_EXPENDITURE_COMMENTS		
		PA_TASKS		
GL Balances	GL_INTERFACE	GL_BALANCES	Journal Import	
BOM	BOM_BILL_OF_MTLS_INTERFACE	BOM_BILL_OF_MATERIALS		
	BOM_INVENTORY_COMPS_INTERFACE	BOM_INVENTORY_COMPONENTS		
	BOM_SUB_COMPS_INTERFACE	BOM_SUBSTITUTE_COMPONENTS		